IP Surveillance API PTZ Service Specification

Version 2.0 2013-12

Content

1		Introduction	4
2		Conformance	4
3		Glossary and Relationship	4
3	3.1	Glossary of Terms	4
3	3.2	Basic PTZ space type XML	5
4		PTZ Service and Resources	5
4	l .1	PTZCtrl	5
4	1.2	/ISAPI/PTZCtrl/capabilities	6
4	1.3	/ISAPI/ PTZCtrl/channels	6
4	1.4	/ISAPI/PTZCtrl/channels/ <id></id>	7
4	1.5	/ISAPI/PTZCtrl/channels/ <id>/capabilities</id>	8
4	1.6	/ISAPI/PTZCtrl/channels/ <id>/homeposition</id>	10
4	1.7	/ISAPI/PTZCtrl/channels/ <id>/homeposition/goto</id>	10
4	1.8	/ISAPI/PTZCtrl/channels/ <id>/continuous</id>	10
4	1.9	/ISAPI/PTZCtrl/channels/ <id>/momentary</id>	11
4	1.10	/ISAPI/PTZCtrl/channels/ <id>/relative</id>	11
4	1.11	/ISAPI/PTZCtrl/channels/ <id>/absolute</id>	12
4	1.12	/ISAPI/PTZCtrl/channels/ <id>/digital</id>	13
4	1.13	/ISAPI/PTZCtrl/channels/ <id>/status</id>	13
4	1.14	/ISAPI/PTZCtrl/channels/ <id>/presets</id>	14
4	1.15	/ISAPI/PTZCtrl/channels/ <id>/presets/<id></id></id>	15
4	1.16	/ISAPI/PTZCtrl/channels/ <id>/presets/<id>/goto</id></id>	15
4	1.17	/ISAPI/PTZCtrl/channels/ <id>/patrols</id>	16
4	1.18	/ISAPI/PTZCtrl/channels/ <id>/patrols/<id></id></id>	17
4	1.19	/ISAPI/PTZCtrl/channels/ <id>/patrols/<id>/start</id></id>	18
4	1.20	/ISAPI/PTZCtrl/channels/ <id>/patrols/<id>/stop</id></id>	18
4	1.21	/ISAPI/PTZCtrl/channels/ <id>/patrols/<id>/pause</id></id>	18
4	1.22	/ISAPI/PTZCtrl/channels/ <id>/patrols/<id>/status</id></id>	18
4	1.23	/ISAPI/PTZCtrl/channels/ <id>/patrols/<id>/schedule</id></id>	19
4	1.24	/ISAPI/PTZCtrl/channels/ <id>/patterns</id>	19
4	1.25	/ISAPI/PTZCtrl/channels/ <id>/patterns/<id></id></id>	20
4	1.26	/ISAPI/PTZCtrl/channels/ <id>/patterns/<id>/recordstart</id></id>	21
4	1.27	/ISAPI/PTZCtrl/channels/ <id>/patterns/<id>/recordstop</id></id>	21
4	1.28	/ISAPI/PTZCtrl/channels/ <id>/patterns/<id>/start</id></id>	21
4	1.29	/ISAPI/PTZCtrl/channels/ <id>/patterns/<id>/stop</id></id>	22
4	1.30	/ISAPI/PTZCtrl/channels/ <id>/PTZOSDDisplay</id>	22
4	1.31	/ISAPI/PTZCtrl/channels/ <id>/parkaction</id>	23
4	1.32	/ISAPI/PTZCtrl/channels/ <id>/ptzlimiteds</id>	23
4	1.33	/ISAPI/PTZCtrl/channels/ <id>/ptzlimiteds/<id></id></id>	24
4	1.34	/ISAPI/PTZCtrl/channels/ <id>/ptzlimiteds/<id>/Initialization</id></id>	25
4	1.35	/ISAPI/PTZCtrl/channels/ <id>/ptzlimiteds/<id>/confirm</id></id>	25
4	1.36	/ISAPI/PTZCtrl/channels/ <id>/ptzlimiteds/<id>/stop</id></id>	25

4.37	/ISAPI/PTZCtrl/channels/ <id>/saveptzpoweroff</id>	26
4.38	/ISAPI/PTZCtrl/channels/ <id>/timetasks</id>	26
4.39	/ISAPI/PTZCtrl/channels/ <id>/timetasks/<id></id></id>	27
4.40	/ISAPI/PTZCtrl/channels/ <id>/timetasks/<id>/copytask</id></id>	28
4.41	/ISAPI/PTZCtrl/channels/ <id>/auxcontrols</id>	29
4.42	/ISAPI/PTZCtrl/channels/ <id>/auxcontrols/<id></id></id>	29
4.43	/ISAPI/PTZCtrl/channels/ <id>/onepushfoucs/start</id>	30
4.44	/ISAPI/PTZCtrl/channels/ <id>/onepushfoucs/reset</id>	31
4.45	/ISAPI/PTZCtrl/channels/ <id>/ManualTrace</id>	31
4.46	/ISAPI/PTZCtrl/channels/ <id>/position3D</id>	31
4.47	/ISAPI/PTZCtrl/channels/ <id>/autoPan</id>	32

1 Introduction

This specification mainly introduces the PTZ function section of ISAPI Protocol.

2 Conformance

All of interface definition in this specification is consistent with that of ISAPI protocol, the specification is a part of ISAPI protocol. The architecture, glossary and relationship are consistent with ISAPI IPMD documentation.

3 Glossary and Relationship

3.1 Glossary of Terms

- *PTZ channel* = PTZ channel is the basic unit of PTZ functions, and a PTZ channel corresponds to a PTZ control unit.
- *Absolute PTZ* = PTZ control unit that supports absolute PTZ. Absolute positioning can designate horizontal angle, vertical angle and lens range.
- *Relative PTZ* = PTZ control unit that supports relative PTZ. The parameter of relative positioning is an increment, which relatives to the current position of PTZ and can be an increment in the horizontal direction, or vertical direction, or increment of lens distance.
- *Continuous PTZ* = PTZ control unit that supports to configure PTZ control speed, the parameter is speed of PTZ.
- *Momentary Move* = this part is the extension of Continuous PTZ function. The running time can be specified in the command and PTZ movement will stop when reaching the specified time.
- *Preset Point* =Moving to a position can be marked as a preset, the preset includes the following parameters: horizontal direction, vertical direction and lens distance, etc.
- *Patrol* = Patrol is a collection of a serials of preset points; the path of patrol will be in order of presets.
- *Home position* = Special preset.
- *PTZ limitation* =Limit the range of PTZ movement. The up, down, left and right border can be specified.
- *PTZ Time Task* = Support to set time and task to PTZ unit.
- PTZ auxcontrol = PTZ auxiliary function, including light, rain wipers and heat lamp.
- *Digital PTZ* = Digital PTZ is not really used to control mechanical

movement; it is generally based on a large resolution, and displayed images in electronic PTZ is a part of the original images obtained by sensor.

3.2 Basic PTZ space type XML

The definition of PTZ space: "X" represents the horizontal direction; "Y" represents the vertical direction, "Z" on behalf of lens distance. A few basic variables will be introduced in this section.

4 PTZ Service and Resources

Back-end devices support multi-channel PTZ, but front-end devices only contain 1-ch PTZ. For different PTZ channels, capability is a little different.

4.1 PTZCtrl

/ISAPI/PTZCtrl	Service	v2.0
Notes: PTZCtrl control service.		

4.2 /ISAPI/PTZCtrl/capabilities

/ISAPI/PTZCtrl/capabilities		General Resource	v2.0
GET	GET		
Description	It is used to get the list of PTZ channels for the d	levice	
Query	None		
Inbound Data	None		
Success Return	PTZCtrlCap		
Notes:			
If maxPTZChannleNum is 0, PTZ service is unavailable			

PTZCtrlCap XML Block

4.3 /ISAPI/ PTZCtrl/channels

/ISAPI/PTZCtrl/channels General Resource v			v2.0
GET			
Description	It is used to get the list of PTZ channels for the d	evice	
Query	None		
Inbound Data	None		
Success Return	PTZChannelList		
PUT			
Description	It is used to update the list of PTZ channels for the	ne device.	
Query	None		
Inbound Data	PTZChannelList		
Success Return	ResponseStatus		
POST			
Description	It is used to add a PTZ channel for the device.		
Query	None		
Inbound Data	PTZChannel		
Success Return	ResponseStatus		
DELETE			
Description	It is used to delete the list of PTZ channels for the	e device.	
Query	None		
Inbound Data	None		

Success Return	ResponseStatus
Notes:	

PTZ channels may be hardwired, or it may be possible to create channels if the device supports it. To determine whether it is possible to dynamically PTZ channels, check the defined HTTP methods in /ISAPI/PTZCtrl/channels/description.

PTZChannelList XML Block

```
<PTZChannelList version="2.0" xmlns="http://www.isapi.org/ver20/XMLSchema">
<PTZChannel/> <!-- opt -->
</PTZChannelList>
```

4.4 /ISAPI/PTZCtrl/channels/<ID>

/ISAPI/PTZCtrl/channels/ <id> General Resource v2.0</id>			
GET			
Description	n It is used to get a particular PTZ channel configuration for the device.		
Query	None		
Inbound Data	None		
Success Return	PTZChannel		
PUT			
Description	It is used to update a particular PTZ channel configuration for the device.		
Query	None		
Inbound Data	PTZChannel		
Success Return	ResponseStatus		
DELETE			
Description It is used to delete a particular PTZ channel on a device.			
Query None			
Inbound Data	None		
Success Return	ResponseStatus		
Notes:			
<videoinputid> links</videoinputid>	s the PTZ channel to a video channel.		
<pre><pre>ectSpeed> indicates the movement speed level about calling preset</pre></pre>			
<autoscanspeed> indicates the movement speed level about park function</autoscanspeed>			
<keypadcontrolspee< td=""><td colspan="3"><keypadcontrolspeed> indicates the movement speed level to be controlled by keyboard</keypadcontrolspeed></td></keypadcontrolspee<>	<keypadcontrolspeed> indicates the movement speed level to be controlled by keyboard</keypadcontrolspeed>		
<controlprotocol> in</controlprotocol>	<controlprotocol> indicates the control protocol to be used for PTZ.</controlprotocol>		
< controlAddress>	indicates the soft address (enabled means soft address is used)		

PTZChannel XML Block

```
<PTZChannel version="2.0" xmlns="http://www.isapi.org/ver20/XMLSchema">
  <id> <!-- req, xs:integer --> </id>
  <enabled> <!--ro,req, xs:boolean --> </enabled>
  <videoInputID>
                     <!-- req, xs:integer --> </videoInputID>
  <panMaxSpeed> <!--ro,opt, xs:integer, degrees/sec --> </panMaxSpeed>
  <tiltMaxSpeed> <!--ro,opt, xs:integer, degrees/sec --> </tiltMaxSpeed>
  <autoPatrolSpeed> <!-- opt, xs:integer, 0..100 --> </autoPatrolSpeed>
  <keyBoardControlSpeed>
      <!-- opt, xs:integer, 0..100 -->
  </keyBoardControlSpeed>
  <controlProtocol> <!-- opt, xs:string, "pelco-d,..." --> </controlProtocol>
  <controlAddress> <!--opt -->
      <enabled>
                     <!-- req, xs:boolean --> </enabled>
                     <!---opt, xs:string 1-255 --> </Address>
      <Address>
  </controlAddress>
  <defaultPresetID> <!-- opt, xs:string;id --> </defaultPresetID>
  <PTZRs485Para>
                        <!-- opt -->
    <baudRate>
                     <!-- req, xs:integer -->
                                                                           </baudRate>
    <dataBits>
                     <!-- req, xs:integer -->
                                                                           </dataBits>
    <parityType>
                     <!-- req, xs:string, "none,even,odd,mark,space" --> </parityType>
                     <!-- req, xs:string, "1,1.5,2" -->
    <stopBits>
                                                                           </stopBits>
    <flowCtrl>
                      <!-- req, xs:string, "none, software, hardware" --> </flowCtrl>
  </PtZRs485Para>
</PTZChannel>
```

4.5 /ISAPI/PTZCtrl/channels/<ID>/capabilities

/ISAPI/PTZCtrl/channels/ID/capabilities General Resource v		v2.0		
GET	GET			
Description	It is used to get the list of PTZ channels for the de	evice		
Query	None			
Inbound Data	None			
Success Return	PTZChanelCap			
Notes:				
XRange: Pan range				
YRange: Tilt range				
ZRange:Zoom range				

PTZChanelCap XML Block

```
<PTZChanelCap version="2.0" xmlns="http://www.isapi.org/ver20/XMLSchema">
  <AbsolutePanTiltPositionSpace> <!--opt-->
     <XRange/><!-- req -->
     <YRange/><!-- req -->
  </AbsolutePanTiltPositionSpace>
  <AbsoluteZoomPositionSpace> <!--opt-->
     <ZRange/> <!-- req -->
 </AbsoluteZoomPositionSpace>
 <RelativePanTiltSpace> <!--opt-->
    <XRange/><!-- req -->
    <YRange/><!-- req -->
 </ RelativePanTiltSpac >
 <RelativeZoomSpace> <!--opt-->
    <ZRange/><!-- req -->
 </RelativeZoomSpace>
<ContinuousPanTiltSpace> <!--opt-->
    <XRange/><!-- req -->
    <YRange/><!-- req -->
</ContinuousPanTiltSpace>
 <ContinuousZoomSpace> <!--opt-->
    <ZRange/><!-- req -->
</ContinuousZoomSpace>
 <MomentaryPanTiltSpace> <!--opt-->
    <XRange/><!-- req -->
    <YRange/><!-- req -->
 </MomentaryPanTiltSpace>
 <MomentaryZoomSpace> <!--opt-->
    <ZRange/><!-- req -->
 </MomentaryZoomSpace>
 <homePostionSupport><!--req,xs:boolean ></homePostionSupport>
 <maxPresetNum><!--req,xs:integer></maxPresetNum>
 <maxPatrolNum><!--req,xs:integer></maxPatrolNum>
 <maxPatternNum><!--req,xs:integer></maxPatternNum>
 <maxLimitesNum><!--req,xs:integer></maxLimitesNum>
 <maxTimeTaskNum><!--req,xs:integer></maxTimeTaskNum>
  <controlProtocol> <!-- opt, xs:string, "pelco-d,..." --> </controlProtocol>
  <controlAddress>
                      <!--opt, xs:string 1-255 --> </controlAddress>
  <PTZRs485Para>
                         <!-- opt -->
    <baudRate>
                      <!-- req, xs:integer -->
                                                                             </baudRate>
                      <!-- req, xs:integer -->
                                                                             </dataBits>
    <dataBits>
    <parityType>
                      <!-- req, xs:string, "none,even,odd,mark,space" --> </parityType>
    <stopBits>
                      <!-- req, xs:string, "1,1.5,2" -->
                                                                             </stopBits>
                       <!-- req, xs:string, "none, software, hardware" --> </flowCtrl>
    <flowCtrl>
```

4.6 /ISAPI/PTZCtrl/channels/<ID>/homeposition

/ISAPI/PTZCtrl/channels/ <id>/homeposition General Resource v</id>			v2.0
PUT			
Description	It is used to set the current horizontal position as point for the device	horizontal coordinate	e zero
Query	None		
Inbound Data	None		
Success Return	ResponseStatus		
DELETE			
Description	It is used to delete system horizontal coordinated default zero point for the device (The photoelectric	•	estore
Query None			
Inbound Data	None		
Success Return	ResponseStatus		
Notes:	Notes:		

4.7 /ISAPI/PTZCtrl/channels/<ID>/homeposition/goto

/ISAPI/PTZCtrl/channels/ <id>/homeposition/goto General Resource</id>			v2.0
PUT			
Description	It is used to move a particular lead to coordinate zero point position for the		zontal
Query	None		
Inbound Data	None		
Success Return	ResponseStatus		
Notes:			

4.8 /ISAPI/PTZCtrl/channels/<ID>/continuous

/ISAPI/PTZCtrl/channels/ <id>/continuous</id>	General Resource	v2.0
PUT		

Description	It is used to control PTZ move around and zoom for the device.
Query	pan, tilt, zoom
Inbound Data	PTZData
Success Return	ResponseStatus
Notes:	

PTZData XML Block

```
<PTZData version="2.0" xmlns="http://www.isapi.org/ver20/XMLSchema">
        <pan> <!-- opt, xs:integer, -100..100 --> </pan>
        <tilt> <!-- opt, xs:integer, -100..100 --> </tilt>
        <zoom> <!-- opt, xs:integer, -100.. 100--> </zoom>
        </PTZData>
```

4.9 /ISAPI/PTZCtrl/channels/<ID>/momentary

/ISAPI/PTZCtrl/channels/ <id>/momentary</id>		General Resource v2.0
PUT		
Description	It is used to control PTZ move around and zoo device.	m in a period of time for the
Query	pan, tilt, zoom, duration	
Inbound Data	PTZData	
Success Return	ResponseStatus	
Notes:		

PTZData XML Block

4.10 /ISAPI/PTZCtrl/channels/<ID>/relative

/ISAPI/PTZCtrl/channels/ <id>/relative</id>		General Resource	v2.0
PUT			
Description	It is used to move the position which is define	ed by positionX, position	nY to
Description	the screen center and relative zoom for the dev	ice.	

Query	positionX, positionY, relativeZoom
Inbound Data	PTZData
Success Return	ResponseStatus
Notes:	
Mouse clicking funct	ion

PTZData XML Block

4.11 /ISAPI/PTZCtrl/channels/<ID>/absolute

/ISAPI/PTZCtrl/channels/ <id>/absolute</id>		General Resource	v2.0
PUT			
Description	It is used to move a particular PTZ channel to a defined by Absolute for the device.	absolute position wh	ich is
Query	elevation, azimuth, absoluteZoom		
Inbound Data	PTZData		
Success Return	ResponseStatus		

Notes:

Absolute position function

<AbsoluteHigh> is high precision positioning which is accurate to a bit after the decimal point;
For example elevation -900..2700 is corresponding to vertical -90.0-270.0 degree, and azimuth
0..3600 is corresponding to horizontal 0.0-360.0 degree, absoluteZoom is corresponding to zoom
0.0..100.0;

PTZData XML Block

4.12 /ISAPI/PTZCtrl/channels/<ID>/digital

/ISAPI/PTZCtrl/channels/ <id>/digital General Resource v</id>		v2.0	
PUT			
Description	It is used to move the position number which position to the screen center and digital zoom for	• •	ionX,
Query	position, positionY, digitalZoomLevel		
Inbound Data	PTZData		
Success Return	ResponseStatus		
Notes:			
Digital zoom function			
digitalZoomLevel: 0 indicates that maintain the original image ratio.			

PTZData XML Block

4.13 /ISAPI/PTZCtrl/channels/<ID>/status

/ISAPI/PTZCtrl/ch	annels/ <id>/status</id>	General Resource	v2.0
GET			
Description	It is used to get currently PTZ coordinate posit	ion for the device.	
Query	None		
Inbound Data	None		
Success Return	PTZStatus		
Notes:			
<absolutehigh> is high precision positioning which is accurate to a bit after the decimal point;</absolutehigh>			
For example elevation -9002700 is corresponding to vertical -90.0-270.0 degree, and azimuth		nuth	
03600 is corresponding to horizontal 0.0-360.0 degree, absoluteZoom is corresponding to zoom		oom	

PTZStatus XML Block

0.0..100.0;

```
< PTZStatus version="2.0" xmlns="http://www.isapi.org/ver20/XMLSchema">
<AbsoluteHigh>
```

4.14 /ISAPI/PTZCtrl/channels/<ID>/presets

/ISAPI/PTZCtrl/channels/ <id>/presets General Resource v</id>		v2.0	
GET			
Description	It is used to get preset configuration information of a problem channel for the device.	oarticular	PTZ
Query	None		
Inbound Data	None		
Success Return	PTZPresetList		
PUT			
Description	It is used to update preset configuration information of a problem channel for the device.	particular	PTZ
Query	None		
Inbound Data	PTZPresetList		
Success Return	ResponseStatus		
POST			
Description	It is used to add a preset configuration information of a part channel for the device.	particular	PTZ
Query	None		
Inbound Data	PTZPreset		
Success Return	ResponseStatus		
DELETE			
Description	It is used to delete a preset configuration information of a channel for the device.	particular	PTZ
Query	None		
Inbound Data	None		
Success Return	ResponseStatus		
Notes:			

PTZPresetList XML Block

4.15 /ISAPI/PTZCtrl/channels/<ID>/presets/<ID>

/ISAPI/PTZCtrl/cha	nnnels/ <id>/presets/<id></id></id>	neral Resource	v2.0
GET			
Description	It is used to get particular preset configuration info PTZ channel for the device.	rmation of a part	icular
Query	None		
Inbound Data	None		
Success Return	PTZPreset		
PUT			
Description	It is used to update particular preset configurate particular PTZ channel for the device.	ion information	of a
Query	None		
Inbound Data	PTZPreset		
Success Return	ResponseStatus		
DELETE			
Description	It is used to delete a particular preset configura particular PTZ channel for the device.	tion information	of a
Query	None		
Inbound Data	None		
Success Return	ResponseStatus		
Notes:			
<id> indicates the pre</id>	eset number.		
<pre><pre><pre><pre>online</pre></pre></pre></pre>	tes the preset name		
Enable is used to indi	cate whether preset have been set.		
PUT is used to set p should be 1 when PU	preset and update title of new preset. (Enable value T)	import to PTZI	Preset

PTZPreset XML Block

4.16 /ISAPI/PTZCtrl/channels/<ID>/presets/<ID>/goto

/ISAPI/PTZCtrl/channels/ <id>/presets/<id>/goto</id></id>	General Resource	v2.0
PUT		

Description	It is used to move a particular PTZ channel to a ID preset position for the device.	
Query	None	
Inbound Data	None	
Success Return	ResponseStatus	
Notes:		

4.17 /ISAPI/PTZCtrl/channels/<ID>/patrols

/ISAPI/PTZCtrl/cha	nnnels/ <id>/presets General Resource v2.0</id>
GET	
Description	It is used to get patrol configuration information of a particular PTZ
	channel for the device.
Query	None
Inbound Data	None
Success Return	PTZPatrolList
PUT	
Description	It is used to update patrol configuration information of a particular PTZ
Description	channel for the device.
Query	None
Inbound Data	PTZPatrolList
Success Return	ResponseStatus
POST	
Description	It is used to add a patrol point configuration for a particular PTZ channel.
Query	None
Inbound Data	PTZPatrol
Success Return	ResponseStatus
DELETE	
Description	It is used to delete patrol configuration for a particular PTZ channel.
Query	None
Inbound Data	None
Success Return	ResponseStatus

PTZPatrolList XML Block

```
<PTZPatrolList version="2.0" xmlns="http://www.isapi.org/ver20/XMLSchema">
<PTZPatrol> <!-- opt -->
</PTZPatrolList>
```

4.18 /ISAPI/PTZCtrl/channels/<ID>/patrols/<ID>

/ISAPI/PTZCtrl/cha	annels/ <id>/patrols/<id> General Resource v2.0</id></id>	
GET		
Description	It is used to get a particular patrol route configuration of a particular PTZ channel.	
Query	None	
Inbound Data	None	
Success Return	PTZPatrol	
PUT		
Description	It is used to update a particular patrol configuration of a particular PTZ channel.	
Query	None	
Inbound Data	PTZPatrol	
Success Return	ResponseStatus	
DELETE		
Description	It is used to delete a particular patrol route configuration of a particular PTZ channel	
Query	None	
Inbound Data	None	
Success Return	ResponseStatus	
Notes:		
<patrolsequence> ind < presetID > indicate <seqspeed> indicates</seqspeed></patrolsequence>	•	
<delay> indicates the dwell time, in seconds</delay>		

PTZPatrol XML Block

4.19 /ISAPI/PTZCtrl/channels/<ID>/patrols/<ID>/start

/ISAPI/PTZCtrl/channels/ <id>/patrols/<id>/start</id></id>		General Resource v2.0
PUT		
Description	It is used to start running particular patrol route	of a particular PTZ channel.
Query	None	
Inbound Data	None	
Success Return	ResponseStatus	
Notes:		

4.20 /ISAPI/PTZCtrl/channels/<ID>/patrols/<ID>/stop

/ISAPI/PTZCtrl/channels/ <id>/patrols/<id>/stop General Resource v</id></id>		General Resource v2.0
PUT		
Description	It is used to stop running particular patrol re	oute of a particular PTZ channel.
Query	None	
Inbound Data	None	
Success Return	ResponseStatus	
Notes:		
It is available to stop the patrol route which is in running state or in pause state.		

4.21 /ISAPI/PTZCtrl/channels/<ID>/patrols/<ID>/pause

/ISAPI/PTZCtrl/channels/ <id>/patrols/<id>/pause General Resource</id></id>		General Resource v2.0
PUT		
Description	It is used to pause particular patrol rout particular channel.	e which is in running state of a
Query	None	
Inbound Data	None	
Success Return	ResponseStatus	
Notes:		
Patrolstart is used to restart patrol route.		
It doesn't support dome at this moment.		

4.22 /ISAPI/PTZCtrl/channels/<ID>/patrols/<ID>/status

/ISAPI/PTZCtrl/channels/ <id>/patrols/<id>/status</id></id>	General Resource	v2.0
GET		

Description	It is used to get particular patrol route state of a particular PTZ channel.	
Query	None	
Inbound Data	PTZPatrolStatus	
Success Return	ResponseStatus	
Notes:		
It doesn't support dome at this moment!!		

PTZPatrolStatus XML Block

4.23 /ISAPI/PTZCtrl/channels/<ID>/patrols/<ID>/sched ule

/ISAPI/PTZCtrl/channels/ <id>/schedule General Resource</id>	
GET	
Description	It is used to get patrol schedule of a particular PTZ channel.
Query	None
Inbound Data	None
Success Return	TimeBlockList
PUT	
Description	It is used to update patrol schedule of a particular PTZ channel.
Query	None
Inbound Data	TimeBlockList
Success Return	ResponseStatus
Notes:	

4.24 /ISAPI/PTZCtrl/channels/<ID>/patterns

/ISAPI/PTZCtrl/channels/ <id>/patterns</id>		General Resource v2.0
GET		
Description	It is used to get pattern configuration of a particular PTZ channel.	
Query	None	
Inbound Data	None	
Success Return	PTZPatternList	
Notes:		
It is similar to presets!!		

PTZPatternList XML Block

```
<PTZPatternList version="2.0" xmlns="http://www.isapi.org/ver20/XMLSchema">
<PTZPattern> <!-- opt -->
</ PTZPatternList >
```

4.25 /ISAPI/PTZCtrl/channels/<ID>/patterns/<ID>

/ISAPI/PTZCtrl/cha	nnnels/ <id>/patterns/<id> General Resource v2.0</id></id>
GET	
Description	It is used to get a particular pattern configuration of a particular PTZ channel.
Query	None
Inbound Data	None
Success Return	PTZPattern
PUT	
Description	It is used to update a particular pattern configuration of a particular PTZ channel.
Query	None
Inbound Data	PTZPattern
Success Return	ResponseStatus
DELETE	
Description	It is used to delete a particular pattern configuration of a particular PTZ channel
Query	None
Inbound Data	None
Success Return	ResponseStatus
Notes: <space> x% indicates</space>	tes the remaining space for pattern

PTZPattern XML Block

4.26/ISAPI/PTZCtrl/channels/<ID>/patterns/<ID>/recordsta

rt

/ISPAI/PTZCtrl/cl	annels/ <id>/patterns/<id>/recordsta General Resource v2.0</id></id>	
rt		
PUT		
Description	It is used to start particular pattern information recording of a particular PTZ channel.	
Query	None	
Inbound Data	None	
Success Return	ResponseStatus	
Notes:		
Remaining space information will be uploaded in real time during the recording process.		

4.27 /ISAPI/PTZCtrl/channels/<ID>/patterns/<ID>/recordstop

/ISAPI/PTZCtrl/channels/ <id>/patterns/<id>/recordsto</id></id>		General Resource v2.0
p		
PUT		
Description	It is used to stop a particular pattern inform PTZ channel	nation recording of a particular
Query	None	
Inbound Data	None	
Success Return	ResponseStatus	
Notes:		

4.28 /ISAPI/PTZCtrl/channels/<ID>/patterns/<ID>/start

/ISAPI/PTZCtrl/channels/ <id>/patterns/<id>/start</id></id>		General Resource	v2.0
PUT			
Description	It is used to start a particular pattern of a particular	ar PTZ channel.	
Query	None		
Inbound Data	None		
Success Return	ResponseStatus		
Notes:			

4.29 /ISAPI/PTZCtrl/channels/<ID>/patterns/<ID>/stop

/ISAPI/PTZCtrl/channels/ <id>/patterns/<id>/stop</id></id>		General Resource	v2.0
PUT			
Description	It is used to stop a particular pattern which particular PTZ channel.	ch is in running status	of a
Query	None		
Inbound Data	None		
Success Return	ResponseStatus		
Notes:			

4.30 /ISAPI/PTZCtrl/channels/<ID>/PTZOSDDisplay

/ISAPI/PTZCtrl/cl	nannels/ <id>/PTZOSDDisplay</id>	General Resource v2.0
GET		
Description	It is used to get OSD display information of	a particular PTZ channel.
Query	None	
Inbound Data	None	
Success Return	PTZOSDDisplay	
PUT		
Description	It is used to update OSD display information	of a particular PTZ channel.
Query	None	
Inbound Data	PTZOSDDisplay	
Success Return	ResponseStatus	
Notes:		
<zoomlable> indica</zoomlable>	tes the zoom progress bar display	
<azimuth> indicates the azimuth display</azimuth>		
<pre><pre><pre><pre>one</pre></pre></pre></pre>	cates the preset title display	

PTZOSDDisplay XML Block

</PTZOSDDisplay>

4.31 /ISAPI/PTZCtrl/channels/<ID>/parkaction

/ISAPI/PTZCtrl/cha	nnels/ <id>/parkaction</id>	General Resource	v2.0
GET			
Description	It is used to get park action information of a PTZ	channel.	
Query	None		
Inbound Data	None		
Success Return	ParkAction		
PUT			
Description	It is used to update park action information of a I	PTZ channel.	
Query	None		
Inbound Data	ParkAction		
Success Return	ResponseStatus		
Notes:			
<parktime> Time spa</parktime>	n that will trigger an park action		
<action> park action</action>	on		
<actionnum> park action number. It is used when park action is patrol, pattern or preset. For</actionnum>		t. For	
others, it is 0			

ParkAction XML Block

4.32 /ISAPI/PTZCtrl/channels/<ID>/ptzlimiteds

/ISAPI/PTZCtrl/channels/ <id>/ptzlimiteds General Resor</id>		General Resource	v2.0
GET			
Description	It is used to get movement limitations of	PTZ channels.	
Query	None		

Inbound Data	None
Success Return	PTZLimitedList
Notes:	

PTZLimitedList XML Block

```
<PTZLimitedList version="2.0" xmlns="http://www.isapi.org/ver20/XMLSchema">
<PTZLimited> <!-- opt -->
</ PTZLimitedList>
```

4.33 /ISAPI/PTZCtrl/channels/<ID>/ptzlimiteds/<ID>

/ISAPI/PTZCtrl/cha	nnels/ <id>/ptzlimiteds/<id></id></id>	General Resource	v2.0
GET			
Description	It is used to get movement limitations of a PTZ of	channel.	
Query	None		
Inbound Data	None		
Success Return	PTZLimited		
PUT			
Description	It is used to update movement limitations of a PT	ΓZ channel.	
Query	None		
Inbound Data	PTZLimited		
Success Return	ResponseStatus		
DELETE			
Description	It is used to clear movement limitations of a PTZ	Cchannel.	
Query	None		
Inbound Data	None		
Success Return	ResponseStatus		
Notes:			
It is used to get or set the parameter that whether movement limitation is enabled or disabled.			
Speed dome add two types of movement limitation.			
<id>=1 Manual cont</id>	<id>=1 Manual control movement limitation <id>=2 Panorama scan movement limitation</id></id>		

PTZLimited XML Block

4.34 /ISAPI/PTZCtrl/channels/<ID>/ptzlimiteds/<ID>/Ini tialization

/ISAPI/PTZCtrl/chann	nels/ <id>/ptzlimiteds/<id>/Initialization</id></id>	General Resource v2.0	
PUT			
Description	Set the start position of a movement	limitation of a PTZ channel.	
Query	None	None	
Inbound Data	None		
Success Return	ResponseStatus		
Notes:			
Only used when movement limitation is enabled.			

4.35 /ISAPI/PTZCtrl/channels/<ID>/ptzlimiteds/<ID>/co

/ISAPI/PTZCtrl/channels/ <id>/ptzlimiteds/<id>/confir General Resource</id></id>		General Resource	v2.0
m			
PUT			
Description	Set other positions of a movement limitation	of a PTZ channel.	
Query	None		
Inbound Data	None		
Success Return	ResponseStatus		
Notes:			
Only used when movement limitation is enabled and Initialization already been used.			
Order of the positions is left \rightarrow right \rightarrow up \rightarrow down. Please save the settings after setup.			
Notes:			
Only used when movement limitation is enabled and Initialization already been used.			
Order of the positions is left \rightarrow right \rightarrow up \rightarrow down. Please save the settings after setup.			
boundary: left,right,up,down			

4.36 /ISAPI/PTZCtrl/channels/<ID>/ptzlimiteds/<ID>/st op

/ISAPI/PTZCtrl/channels/ <id>/ptzlimiteds/<id>/setstop</id></id>		General Resource v2.0
PUT		
Description	Set the start position of a movement	ent limitation of a PTZ channel.

Query	None	
Inbound Data	None	
Success Return	ResponseStatus	
Notes:		
Stop ptz limitation setting, save boundary to device.		

4.37 /ISAPI/PTZCtrl/channels/<ID>/saveptzpoweroff

/ISAPI/PTZCtrl/channels/ <id>/saveptzpoweroff General Resource v2.</id>		
GET		
Description	It is used to get the PTZ power off memory settings information	
Query	None	
Inbound Data	None	
Success Return	savePtzpoweroff	
PUT		
Description	It is used to update the PTZ power off memory settings information	
Query	None	
Inbound Data	savePtzpoweroff	
Success Return	ResponseStatus	
Notes:		
<saveptzpoweroff>Power off memory</saveptzpoweroff>		

$save Ptz Power off\ XML\ Block$

```
<savePtzPoweroff version="2.0" xmlns="http://www.isapi.org/ver20/XMLSchema">
        <savePtzPoweroffType>
        <!-- req, xs:integer, "disable, 30sec, 60sec, 300sec, 600sec"-->
        </savePtzPoweroffType>
        </savePtzPoweroff>
```

4.38 /ISAPI/PTZCtrl/channels/<ID>/timetasks

/ISAPI/PTZCtrl/channels/ <id>/timetasks</id>		General Resource	v2.0
GET			
Description	It is used to get a list of tasks based on a schedule	e	
Query	None		
Inbound Data	None		
Success Return	TimeTaskList		
PUT			
Description	It is used to update a list of tasks based on a schedule		
Query	None		

Inbound Data	TimeTaskList	
Success Return	ResponseStatus	
Notes:	Notes:	
GET is used to get a list of tasks of a whole week(7)		
<enabled>Enable all the tasks</enabled>		
<parktime> Time span for a task to resume.</parktime>		

TimeTaskList XML Block

```
<TimeTaskList version="2.0" xmlns="http://www.isapi.org/ver20/XMLSchema">
<enabled> <!-- req, xs:boolean --> </enabled>
<Parktime> <!-- req, xs:integer, seconds --> </Parktime>
<TimeTaskBlock /> <!-- opt -->
</TimeTaskList>
```

4.39 /ISAPI/PTZCtrl/channels/<ID>/timetasks/<ID>

/ISAPI/PTZCtrl/cha	nnnels/ <id>/timetasks/<id></id></id>	General Resource	v2.0
GET			
Description	It is used to get a list of tasks of one day		
Query	None		
Inbound Data	None		
Success Return	TimeTaskBlock		
PUT			
Description	It is used to update a list of tasks of one day		
Query	None		
Inbound Data	TimeTaskBlock		
Success Return	ResponseStatus		
DELETE			
Description	It is used to delete a list of tasks of one day		
Query	None		
Inbound Data	None		
Success Return	ResponseStatus		

Notes:

Tasks based on a schedule consist of time blocks ad tasked. This task is enabled always.

- <TimeTaskBlock> get all the time span and tasks of one day
- <dayOfWeek> specify the day of a week, ranging from 1 to 7
- <TimeTaskRange> time span of each task. Up to ten time spans and 10 tasks are supported in one day.
- <beginDateTime> specify the begin time of each task, ranig from 0:0:0-23:59:00, format is consistent to ISO 8601.
- <endDateTime> specify the end time of each task, ranig from 0:0:0-23:59:00, format is consistent

```
to ISO 8601. endDateTime should be larger than or equal to beginDateTime.

<TaskType> Tasks type

<TaskNum> Tasks number. Enabled when park action is patrol, pattern, preset or auxoutput, otherwise the value is 0.
```

TimeTaskBlock XML Block

```
<TimeTaskBlock version="2.0" xmlns="http://www.isapi.org/ver20/XMLSchema">
  <dayOfWeek>
    <!-- req, xs:integer, ISO8601 weekday number, 1=Monday, ... -->
  </dayOfWeek>
  <TimeTaskRange>
     <TaskID><!-- req, xs:string;id --></TaskID>
     <br/><beginTime> <!-- req, xs:time, ISO8601 time --> </beginTime>
     <endTime> <!-- req, xs:time, ISO8601 time --> </endTime>
     <Task>
        <TaskType>
          <!-- req, xs:strings, "disable, atuoscan, framescan, randomscan, panoramascan, patrol,
pattern, preset, tiltscan,periodreboot,periodadjust,auxoutput" -->
        </TaskType>
        <TaskNum><!-- dep, xs:integer, 0.8--></TaskNum>
     </Task>
  </TimeTaskRange>
</TimeTaskBlock>
```

4.40 /ISAPI/PTZCtrl/channels/<ID>/timetasks/<ID>/cop ytask

/ISAPI/PTZCtrl/ch	nannels/ <id>/timetasks/<id>/copytask General Resource v2.0</id></id>
GET	
Description	It is used to get the default copy time of a tasks list of a specified PTZ channel.
Query	None
Inbound Data	None
Success Return	TimeTaskCopy
PUT	
Description	It is used to update the default copy time of a tasks list of a specified PTZ channel.
Query	None
Inbound Data	TimeTaskCopy
Success Return	ResponseStatus
Notes:	

<curDayOfWeek> specify the current day of a week;
<copyDayOfWeek> specify the days that will have the same settings as the current day;

TimeTaskCopy XML Block

4.41 /ISAPI/PTZCtrl/channels/<ID>/auxcontrols

/ISAPI/PTZCtrl/cha	annels/ <id>/auxcontrols General Resource vi</id>	2.0
GET		
Description	It is used to get auxillary PTZ control information of a specific PTZchannel.	ied
Query	command	
Inbound Data	None	
Success Return	PTZAuxList	
PUT		
Description	It is used to update auxillary PTZ control information of a specific PTZchannel.	ied
Query	command	
Inbound Data	PTZAuxList	
Success Return	ResponseStatus	
Notes:		

PTZAuxList XML Block

```
<PTZAuxList version="2.0" xmlns="http://www.isapi.org/ver20/XMLSchema">
<PTZAux /> <!-- opt -->
</PTZAuxList>
```

4.42 /ISAPI/PTZCtrl/channels/<ID>/auxcontrols/<ID>

/ISAPI/PTZCtrl/cha	nnnels/ <id>/auxcontrols/<id></id></id>	General Resource v2.0
GET		
Description	It is used to get auxillary PTZ control	information of a specified

	PTZchannel.
Query	Command
Inbound Data	None
Success Return	PTZAux
PUT	
Danasintias	It is used to update auxillary PTZ control information of a specified
Description	PTZchannel.
Query	Command
Inbound Data	PTZAux
Success Return	ResponseStatus
Notes:	
Auxillary Types:	
LIGHT	
WIPER	
FAN	
HEATER	
<status> may be "wr</status>	ite only", due to ptz type

PTZAux XML Block

4.43 /ISAPI/PTZCtrl/channels/<ID>/onepushfoucs/star

t

/ISAPI/PTZCtrl/channels/ <ii< th=""><th>)>/onepushfoucs/start</th><th>General Resource</th><th>v2.0</th></ii<>)>/onepushfoucs/start	General Resource	v2.0
PUT			
Description	It is used to start focusing by pushing	a key.	
Query	None		
Inbound Data	None		
Success Return	ResponseStatus		
Notes:			

4.44 /ISAPI/PTZCtrl/channels/<ID>/onepushfoucs/rese

t

/ISAPI/PTZCtrl/channels/ <id>/onepushfoucs/reset</id>		General Resource	v2.0
PUT			
Description	It is used to stop focusing by pushing a key.		
Query	None		
Inbound Data	None		
Success Return	ResponseStatus		
Notes:			

4.45 /ISAPI/PTZCtrl/channels/<ID>/ManualTrace

/ISAPI/PTZCtrl/channels/ <ii< th=""><th>D>/ManualTrace</th><th>General Resource v2.0</th></ii<>	D>/ManualTrace	General Resource v2.0
PUT		
Description	It is used to set manual tracking of a particular PTZ channel.	
Query	None	
Inbound Data	ManualTrace	
Success Return	ResponseStatus	
Notes:		

ManualTrace XML Block

4.46 /ISAPI/PTZCtrl/channels/<ID>/position3D

/ISAPI/PTZCtrl/channels/<1	D>/position3D General Resource v2.0	
PUT		
Description	It is used to set 3D zoom of a particular PTZ channel.	
Query	None	
Inbound Data	Position3D	
Success Return	ResponseStatus	
Notes:		

Position3D XML Block

4.47 /ISAPI/PTZCtrl/channels/<ID>/autoPan

/ISAPI/PTZCtrl/ch	annels/ <id>/autoPan</id>	General Resource	v2.0
PUT			
Description			
Query	None		
Inbound Data	autoPanData		
Success Return	ResponseStatus		
Notes:			

autoPanData XML Block

```
<autoPanData version="2.0" xmlns="http://www.isapi.org/ver20/XMLSchema">
<autoPan> <!-- req, xs:integer, 0..100 --></autoPan>
</autoPanData>
```